

FTP Uploader

User Guide

Table of contents:

1. Introduction
2. Installation steps
3. Usage
4. Uploading

1. Introduction

FTP Uploader is an FTP client that is used for uploading large amounts of files to your website without getting disconnected. Follow these simple instructions to begin.

2. Installation Steps

2.1 Running the installer

Double click the FTP Uploader icon to open the program.

3. Usage

3.1 Server Parameters

In order to begin uploading you will need to input the following server parameters:

FTP Server host
Server's top folder to upload files
User Name
Password
Source folder to upload

Here is a brief explanation of the server parameters:

Note:

If you are unsure about any of the server parameters you should contact your web host to find out this data.

FTP Server host = This is the URL or domain name of the site that you wish to upload to.
Example: <ftp.yourdomain.com>

Server's top folder to upload files = This is the directory which you need to upload to.
Most servers top folder is one of the following:

/

/public_html
/www
/htdocs

User Name = This is the username that was assigned to the domain by your web host.

Password = This is the password associated with the username for the domain.

Source folder to upload = This is the location on your PC that contains the files to upload.

3.2 Show completed files in the log

FTP Uploader will show a log while the transfers are occurring. You may check the box Show completed files in the log if you wish to review them while uploading.

3.3 Threads and Attempt Numbers

You can specify the number of attempts and threads you want FTP Uploader to use.

Threads:

The default is 1. The more threads you specify the more bandwidth FTP Uploader will use to transfer. More threads will mean a faster transfer. You may select numerical values 1 – 20.

Attempts:

If some of the files fail to upload you may specify the number of attempts FTP Uploader will try to reconnect and finish the transfers. You may select numerical values 1 – 30.


3.4 Recursively upload subfolders

If you want FTP Uploader to upload the files to all subfolders on your site you may select this option.

3.5 Keep subfolder's structure


If you are uploading a directory that has subfolders FTP Uploader will create these folders on your server and upload them accordingly.

3.6 Using the count feature

If you would like to know the Number of files and the Common size of files you can press the  Count after you have specified the Source folder.

4. Uploading

4.1 Starting the upload process

To begin uploading press the  button.

I hope you enjoy FTP Uploader!